NAME

lpusers – set printing queue priorities

SYNOPSIS

lpusers –**d** *priority-level*
lpusers –**q** *priority-level* –**u** *login-ID-list*
lpusers –**u** *login-ID-list*
lpusers –**q** *priority-level*
lpusers –**l**

AVAILABILITY

SUNWlps

DESCRIPTION

The **lpusers** command sets limits to the queue priority level that can be assigned to jobs submitted by users of the LP print service.

The first form of the command (with –**d**) sets the system-wide priority default to *priority-level*, where *priority-level* is a value of 0 to 39, with 0 being the highest priority. If a user does not specify a priority level with a print request (see **lp**(1)), the default priority level is used. Initially, the default priority level is 20.

The second form of the command (with –**q** and –**u**) sets the default highest *priority-level* (0-39) that the users in *login-ID-list* can request when submitting a print request. The *login-ID-list* argument may include any or all of the following constructs:

login-ID	A user on any system
system_name!*login-ID*	A user on the system *system_name*
system_name!**all**	All users on system *system_name*
all!*login-ID*	A user on all systems
all	All users on all systems

Users that have been given a limit cannot submit a print request with a higher priority level than the one assigned, nor can they change a request that has already been submitted to have a higher priority. Any print requests submitted with priority levels higher than allowed will be given the highest priority allowed.

The third form of the command (with –**u**) removes any explicit priority level for the specified users.

The fourth form of the command (with –**q**) sets the default highest priority level for all users not explicitly covered by the use of the second form of this command.

The last form of the command (with –**l**) lists the default priority level and the priority limits assigned to users.

OPTIONS

–**d** *priority-level* Set the system-wide priority default to *priority-level*.

–**q** *priority-level* –**u** *login-ID-list*
Set the default highest *priority-level* that the users in *login-ID-list* can request when submitting a print request.

–u *login-ID-list*	Remove any explicit priority level for the specified users.
–q *priority-level*	Set the default highest priority level for all users not explicitly covered.
–l	List the default priority level and the priority limits assigned to users.

SEE ALSO **lp**(1)